

# **CND PLEXIGEL**<sup>TM</sup> Shaper-Natural Nail Overlay

A service option for natural nails requiring strength, protection and light shape enhancement.

#### CND™ PRODUCTS REQUIRED

- COOLBLUE™ Hand Cleanser
- OFFLY FAST™ Moisturizing Remover
- SCRUBFRESH™ Nail Surface Cleanser
- CND™ Files and Buffers
- . CND PLEXIGEL™ Bonder
- . CND PLEXIGEL™ Shaper
- CND PLEXIGEL™ Protector Top Coat

#### **ACCESSORIES/EQUIPMENT REQUIRED**

- CND™ LED Lamp
- Hand towels
- Hand soap
- Plastic-backed, lint-free pads
- 99% Isopropyl Alcohol
- · Cuticle pusher
- Manicure nippers
- Nail clippers
- Curette
- E-File\*

\*Optional



#### Step 1

# PERFORM A MANICURE.


- Have the client wash their hands with soap and running water for 20-30 seconds and towel dry.
- 2. Massage COOLBLUE™ Hand Cleanser into the client's hands.
- 3. If necessary, remove any existing nail color from the natural nail using an acetone-based polish remover (OFFLY FAST™ Moisturizing Remover) and a plastic-backed lint-free pad.\*
- 4. If necessary, trim the length from each nail, using nail clippers.
- 5. Shape the free edge of each nail with a fine 240-grit file (Kanga™ File or Koala Buffer™).
- 6. Gently slide a **cuticle pusher** along the nail plate toward the proximal nail fold (cuticle area) and along each lateral fold (sides of nail) to lift and loosen any cuticle (non-living tissue) from the nail plate.\*\*
- 7. Gently guide a curette along the nail plate to remove non-living tissue on the nail.
- 8. If necessary, use a manicure nipper to carefully remove any loose pieces of skin or hangnails.











\* Acetone-based polish removers like CND™ OFFLY FAST™ is the quickest and safest way to remove nail color. Non-acetone-based polish removers will dissolve enamel more slowly and "smear" the color onto the cuticle area risking over-exposure.

\*\* For clients who build excessive cuticle between services, apply a small amount of CuticleAway\*\* Professional Cuticle Remover evenly around the cuticle of each nail and perform cuticle service. Be sure to scrub nails thoroughly with soap and running water for 20-30 seconds to thoroughly remove the cuticle remover and towel dry.




## REMOVE SHINE.

9. Remove shine from the natural nail surface with a fine 240-grit buffer (Koala Buffer™) in the direction of the natural nail growth. Optional: Use an enhancement prep bit at low speed with very gentle pressure with E-File.

# ELIMINATE SURFACE CONTAMINANTS AND PURIFY NAIL PLATE LAYERS.

10. Thoroughly cleanse and temporarily dehydrate the nail plate layers with SCRUBFRESH™ using a lint-free, plastic-backed pad. Pull back the skin and scrub the nail as if removing red nail polish.







#### Step 2

# APPLY CND PLEXIGEL™ BONDER

- 1. Roll the bottle gently to blend.
- Apply a thin layer of CND PLEXIGEL™ Bonder to all five nails, sealing the edge after each application. Always leave a tiny free margin around the perimeter of the nail to avoid the skin.
- Cure for 10 seconds in the CND™ LED Lamp using preset button 1. Do not remove the top film after removing nails from the lamp.





#### Step 3

# **APPLY CND PLEXIGEL™ SHAPER**

- Apply a thin, even layer of CND PLEXIGEL™ Shaper to the natural nail, sealing the free edge after application. Always leave a tiny free margin around the perimeter of the nail to avoid the skin.
- 2. Apply to all five nails and cure for one minute in the CND™ LED Lamp using preset button 2B. Do not remove the top film after removing the nails from the lamp.
- 3. Apply a second layer of shaper to prefect the shape, using a light touch to float the gel over the nail.
  - a. Flash cure two fingers at a time to prevent the gel from running, using preset button 1.
- 4. Apply shaper to all five nails and cure for one minute using present button 2B.









#### Step 4

### PERFECT THE SHAPE

(Optional)

- 1 If shape refinement is needed, remove top film with cotton pad saturated with 99% Isopropyl Alcohol.
- 2 Buff the surface of the nail to smooth out any imperfections using a 180-grit file or buffer (Boomerang Padded File or **Bilzzard™ File**)

  Optional: Use a medium grit diamond bit at ½ speed with E-File
- 3 Remove dust and cleanse the nail with 99% Isopropyl Alcohol.

#### Step 5


# **APPLY CND PLEXIGEL™ PROTECTOR TOP COAT**

Use to seal and protect clear enhancements or prior to applying CND™ VINYLUX™ Long Wear Polish.

- 1. Roll the bottle gently to blend.
- 2. Apply a layer of CND PLEXIGEL™ Protector Top Coat to all five nails sealing the free edge after application.
- 3. Cure for one minute in the CND™ LED Lamp using preset button 3.
- 4. Lightly wipe to remove top film with lint-free pad or cosmetic sponge saturated with 99% Isopropyl Alcohol.









#### Step 6

# **ADD COLOR**

(Option for gel polish)

If using CND ™ SHELLAC™ Gel Polish, skip Protector Top Coat and CND™ SHELLAC™ Base Coat.

- Shake CND™ SHELLAC™ Color vigorously to blend.
- 2. Apply two thin layers of color coat to all five nails using the 5-point polish method.
- 3. Cure each layer for one minute in the CND™ LED Lamp using preset button 2S.
- 4. Apply a layer of CND™ SHELLAC™ Top Coat to all five nails.
- 5. Cure for one minute in the  $\mathbf{CND}^{\mathsf{TM}}$  LED Lamp using preset button 3.
- 6. Lightly wipe to remove top film with cotton pad or cosmetic sponge saturated with 99% Isopropyl Alcohol.
- 7. Apply a drop of **SOLAROIL**™ to condition the nail.















WWW.CND.COM | www.instagram.com/CNDWORLD